

Content

1 Device - Revision Record / What is new? 1

1.1 Hardware 1

1.2 Software..... 1

2 DTM - Engineer IT Device Type Manager 1

2.1 Supported devices 1

2.2 Version record / What is new? 1

2.3 Requirements 1

2.3.1 PC-Hardware, Operating system 1

2.3.2 Frame application / compatibility 1

2.3.3 Software package contents 2

2.4 Installation and configuration 2

2.4.1 Installation 2

2.4.2 Installed files 2

2.4.3 Uninstall instructions 2

2.5 Update- / Upgrade instructions 2

2.6 Known problems and limitations 2

2.7 Getting help / further information 2

2.8 How to get the Software (driver)? 2

2.9 Licensing the DTM 2

1 Device - Revision Record / What is new?

1.1 Hardware

All released with Hardware Revision B.2x. or lower

1.2 Software

Released Revision	Released Date	Remarks
A.11	11/2001	First release
A.21	07/2003	Bugfix
A.30	11/2003	Bugfix
A.34	12/2004	Design Enhancement (not DTM relevant)
B.10	2/2007	Functional enhancement
B.20	10/2007	Namur NE43 compliant

2 DTM - Engineer IT Device Type Manager

2.1 Supported devices

- FCM2000
- with device Software revision ≤ B.2x

2.2 Version record / What is new?

Compatible with FDT 1.2 frame applications.

Released Version	Released Date	Remarks
01.03.00	23.03.2003	First release
01.04.01	09.02.2004	Adapted to match FDT1.2 requirements
01.04.01	08/2005	Silent setup implemented

2.3 Requirements

2.3.1 PC-Hardware, Operating system

- Minimum requirement
- Intel Pentium III Processor 450 MHz or compatible.
- 256 MB RAM memory.
- 300 MB free hard disk space.
- Windows 2000 / XP.
- Internet Explorer 6.0.
- Adobe Reader latest version
- full administrator rights

The ABB FDT 1.2 DTM FCM2000-HART is released for Windows 2000 and Windows XP (Home / Professional) as PC / Notebook installation.

2.3.2 Frame application / compatibility

The FDT compatibility was tested with the dtmINSPECTOR Rev. 1.01.21.
Therefore the ABB DTM should be usable in all Frame Applications according the requirements of FDT 1.2.
Please read also the respective Frame Application documentation.

2.3.3 Software package contents

- setup.exe

2.4 Installation and configuration

2.4.1 Installation

- Make sure that the minimum hardware requirements are met.
- Start Windows (with administrator rights!).
- Cancel all running programs.
- Insert CD-ROM.
- Start "Setup.exe" in the DTM\DTM FCM2000-HART directory of the CD or in the folder you choosed for the software uploaded from the Internet.
- Follow the instructions.

2.4.2 Installed files

2.4.3 Uninstall instructions

For uninstalling in the operating system: Start-> Settings
-> Control Panel -> Add/Remove Programs -> Install/Uninstall"
-> Select the DTM and Uninstall.

In any case first uninstall all DTMs before uninstalling the frame application SMART VISION

2.5 Update- / Upgrade instructions

Uninstall is not needed before update / upgrade. It can be handled like a new installation, existing projects will be kept.

Hints regarding new versions may be found under <http://www.abb.com/Fieldbus>

2.6 Known problems and limitations

- Measured values for flow (mass and volume) are given by the device as positive values for flow and reverse flow.
- Entries in edit boxes have to be acknowledged by Enter or TAB to be valid.
- In the trend display the current measured values are not shown in the legend.
- An automatic loading of preconfigured data to the transmitter from Symphony/Freelance is not possible during planning phase as only with active DTM and online connection to the transmitter a complete plausibilisation of the device version is possible. For configuration and loading of data the DTM therefore has to be started during start-up phase and an online connection has to be established.
- If starting of a DTM fails with a runtime error 6 which occurs together with a control SV4_digital.OCX, the PC needs to reboot.

2.7 Getting help / further information

- Press "F1" for online help. Help concerning the implementation of the DTM in the system environment (e.g. SMART VISION, AC800F, CMC60, CMC70) can be found in the respective documentation.

Hints regarding commissioning

- Initialisation of the DTM for the FCM2000:
For starting the DTM, the DTM for the FCM2000 as HART device has to be used when creating the project tree. For initialisation the point "More" has to be selected in the menu under "Device". Depending on the operating speed of the PC this could take some seconds.
- Configuration of the FCM2000:
The DTM is started by clicking the right mouse key or via the menu point "Device", in each case with "Edit".
When an online connection has been established it is now recommended to make an upload.
- When a device has been connected for the first time, and an upload has been done, it is recommended to save all data using the menu file/save as dataset. (database suffix *.dat)

2.8 How to get the Software (driver)?

Please use one of the following ways to get the Software (driver):

- Available on the newest DSV4xx (SMART VISION) & DTM CD-ROM
- As download from <http://www.abb.com/Fieldbus>
->[select Fieldbus protocol]
->[select field device]
->[select device group / name]
use link read more / downloads
-> go to flag "Fieldbus & HART Files"
- The Aspect Object (*.afw) online file contains all driver and information. For the *.afw file
-> go to flag "Downloads"

2.9 Licensing the DTM

- The DTM is usable without any license in any frame application.
- After the installation the ABB DTM runs 90-days in demo mode (full functionality) and needs to be purchased within this period, when the storage of data on a PC / Notebook being requested.
- By purchasing the DSV401 (SMART VISION) single PC license the ABB DTM is also operable without restriction and does not have to be ordered separately!

**ABB has Sales & Customer Support
expertise in over 100 countries worldwide.**

www.abb.com/instrumentation

The Company's policy is one of continuous product improvement and the right is reserved to modify the information contained herein without notice.

Printed in the Fed. Rep. of Germany (04.2008)

© ABB 2008



ABB Ltd.
Oldends Lane, Stonehouse
Gloucestershire, GL10 3TA
UK
Tel: +44 (0) 1453 826661
Fax: +44 (0) 1453 829671

ABB Inc.
125 E. County Line Road
Warminster, PA 18974
USA
Tel: +1 215 674 6000
Fax: +1 215 674 7183

ABB Automation Products GmbH
Dransfelder Str. 2
37079 Göttingen
Germany
Tel: +49 551 905-534
Fax: +49 551 905-555